



Product Registration

User Manual

UM0094_3



Foreword

Copyright © 2015 TDSi. All rights reserved.
Time and Data Systems International Ltd operate a policy of continuous improvement and reserves the right to change specifications, colours or prices of any of its products without prior notice.

Guarantee

For terms of guarantee, please contact your supplier.

Trademarks

Microsoft and Windows are registered trademarks of Microsoft Corporation.
All other brands and product names are trademarks or registered trademarks of their respective owners.

Document Control

Issue	Date Issued	Change Summary	Issued by
1	27 th November 2015	Initial release	GFH
2	15 th December 2015	Activate and Deactivate and document control added	GFH
3	21 st June 2015	Design update and website link added to page 1	GFH

Contents

1	Introduction.....	1
2	Register	2
3	Managing Sites.....	4
4	Activate Software	6
5	Deactivate Software.....	8
6	Extensions.....	11

1 Introduction

The EXgarde Product Registration Website has been developed to improve the product registration process and can be found at <https://tdsi-product-registration.com>.

Key features of the website are:

-  Manage products of different site
-  Register serial numbers
-  Deactivate products

2 Register

Before you are able to login to the TDSi product registration website you will need to register. To do this click on the Click here link.

Login.

Enter your details to log in

Email Address:

Password:

RememberMe [Forgotten Password?](#)

Not yet registered [Click here](#)

Complete the Registration form and click on the Register button

Register.

Enter your details to register.

Registration Form

First Name:


Last Name:

Email Address:

Confirm Email Address:

Company Name:

You will be presented with a confirmation window indicating an email will be sent to the specified email address.



Once you have received the email follow the instructions and click on the link, this will return you to the product registration website to complete the registration process.

Complete Registration

Please enter the details to complete your registration.

Email Address:

Company Name:


New Password
(Leave blank to remain the same):

Confirm Password:


Complete the form and click on the submit button.
You will now be able to login to the TDSi product registration website.

3 Managing Sites


Once you have logged in correctly, you will be presented with the TDSi Product Registration main page. Here you will be able to view your registered site, search for serial numbers and add addition sites.



The registered sites will automatically be displayed when you log in. You can view registered software from each of the sites by clicking on the Registrations link to the left of each site.




To add a new site, select the Add site link. Here you will be able to enter details of the new site. Click add when you have completed the form.




4 Activate Software

Once your sites have been set up you can add software to each site.



To add software to each site, click on the Registrations link relevant to the site.



In the Site Registrations window, you will need to click on the Add Software button to begin the process.

The window below will pop up and required the Serial number from the spine of the EXgarde Software package and Machine Code from the product activation window.

Activate Software Registration

Serial Number: ENT-YDY787-WY5W5-UC3E6-6NGXY-WWJ3-2NPC8

Machine Code: TAU0E-2WFU-SWEQ7-NUY7C-MEV7D

Machine ID: 1 (Any)

Activate

Click activate to complete the process.

A small window will pop up, containing the Activation code. This will need to be copied in to the EXgarde activation window.

Activation ...

Activation Code: ENT-NE2YU-HFE6A-AXQMV-RYN8L-SMSXV-9FHV7

Exgarde

Activate Offline

Please contact customer service and provide them with the information displayed below.

Serial Number
ENT-AA1W4-22ASM-JNGDG-HPSKQ-TC6H3-2NJH8

Machine Code
TAU8W-5VSQR-RENA5-XRP3T-VDU3F

Activation Code **Machine ID** 1 (Any)

ENT-XXXXX-XXXXX-XXXXX-XXXXX-XXXXX-XXXXX

Get Help

[Email Customer Service](mailto:support@tdsico.uk)
support@tdsico.uk


[Customer Service Website](http://www.tdsico.uk)
www.tdsico.uk

Go Back **Activate**


Once you have entered the Activation code, click the Activate button.

5 Deactivate Software

TDSi recommend deactivating software in cases where the EXgarde software is being move from one machine to another. To do this click on the deactivate link to the right of the serial number to open the deactivation window.




The deactivation code is obtained via the Licence server. Select File and scroll down to De-activate Licence to open the deactivation window.




Click on the Deactivate button at the bottom of the window to start the process



You will then be presented with a conformation window. Click yes to continue.




A new window will open containing the Deactivation code.



Deactivate Software

Copy the deactivation code and past it in to the Deactivation code box and then enter the date and click Deactivate.



Deactivate Software Registration

Deactivation Code EXP-D5WV1-HY72X-14WY


Deactivation Date 12/02/2015

Deactivate

A new window will confirm the deactivation was completed successfully.



The recently deactivated licence will now be displayed in the Site registrations window with the Activate link visible.



Product Registration | TDSi

www.tdsi-product-registration.com/Site/Index

greg@tdsi.co.uk Log off

Sites Language

Site Registrations - Thomas, Poole

Software

[Add Software](#)

Serial Number	Activation Code		
ENT-YDY787-WY5W5-UC3E8-8NGXY-WWJ3-2NPC8		Activate	Extensions
EXP-751CXP-GOSEH-324JA-A9PJL-C0PVJ-7NPDJ	EXP-D99MU-1V2U9-H6LPS-STLHY-A9FMV-TPJLQ	Deactivate	Extensions
ENT-WHSK5N-UVW98-2NREN-TN328-N98AG-TN8UV	ENT-PMPTY-Q2VQD-TPJLQ-69MV9-F6U2X-F8AT4	Deactivate	Extensions
ENT-LXUTSL-STLHY-V9FMV-AH3TQ-48H39-WHSK59	ENT-F9MXW-7NVQ1-2WATK-2PN2K-LE5FJ-Q0TVJ	Deactivate	Extensions

Registered Products


[Add Registered Product](#)

You don't have any registered products for this site. To start, click the "Add Registered Product" link above.


Version: 1.0.4.0 © 2015 - TDSi

6 Extensions

To enable additional features of your EXgarde software please contact TDSi sales with your requirements. Once the extension order has been processed the serial number on your site will be updated. You will need to then click on the Extension link associated with the serial number to view the new extension.




In the Extensions window you will be able to view all the current and any newly generated extensions.




Extensions


To activate a new extension, click on the Generate Extension Code. This will open a new window allowing you to enter the Limit code.




Once you have entered your limit code click generate. A new window will pop up with the extension code.



You can now enter the new extension code into the EXgarde Licence server upgrades window.



The EXgarde licence sever will now be updated, in this example showing 64 IP Locks.



This page intentionally left blank

This page intentionally left blank



Because everyone deserves peace of mind

TDSi UK

Unit 10 Concept Park, Innovation Close, Poole, Dorset BH12 4QT United Kingdom
t: +44 (0)1202 723535 f: +44 (0)1202 724975 e: sales@tdsi.co.uk

TDSi France

Immeuble ATRIA, 2 rue du Centre, 93160 NOISY LE GRAND France
t: +33 (0)1 58 84 20 90 f: +33 (0)1 58 84 20 91 e: info@tdsi-france.com

